

National Stock Exchange of India Limited

Circular

Department: ELECTRONIC GOLD RECEIPTS	
Download Ref No: NSE/EGR/74355	Date: May 22, 2026
Circular Ref. No: 09/2026	

All Members,

Mock trading on Saturday, May 23, 2026 – No new version release

Exchange will be conducting a mock trading session in the Electronic Gold Receipts (EGR) segment on Saturday, May 23, 2026 as per following schedule:

Mock Date: May 23, 2026	
Particulars	Time in Hrs
Trading Session-1 from Primary Site	
Pre-open session Open	08:45
Pre-open session Close* <i>*Random closure in last one minute</i>	08:53
Normal Market open time	09:00
Normal Market close time	10:05
Trading Session-2 from DR Site	
Pre-open session Open	10:45
Pre-open session Close* <i>*Random closure in last one minute</i>	10:53
Normal Market open time	11:00
Normal Market close time	11:30
Trade modification end time	11:10
Re-login Timings	
Live Re-login start time	13:00
Live Re-login close time	13:30

Members are required to take note of the below important points:

A) NEAT+ version details

Version	Download Path on NSE Extranet:
1.0.0	/egftp/egcommon/NEATPlus100

National Stock Exchange of India Limited

- B) Members are requested to refer to NEAT Adapter circular NSE/MSD/74225 dated May 14, 2026 for NEAT Adapter Exe application and accordingly use the following combination NEAT Adapter and ports applicable in EGR segment.

Login through	Applicable GR PORT
New NEAT Adapter application Version 1.0.25 for Windows Neat Adapter Version 1.0.25 for Linux Neat Adapter	11887

Members are advised to refer to the following Annexures for important instructions regarding the mock trading:

[Annexure 1: Important instructions regarding mock trading session.](#)

[Annexure 2: Interactive Parameters for Login](#)

[Annexure 3: Parameters for market data broadcast for EGR segment](#)

[Annexure 4: Installation procedure for NEATPlus EG Version 1.0.0](#)

[Annexure 5: Important guidelines in case of switchover of trading system to Disaster Recovery \(DR\) Site](#)

**For and on behalf of
National Stock Exchange of India Limited**

**Khushal Shah
Associate Vice President**

Toll Free No	Email id
1800-266-0050 (Option1)	msm@nse.co.in

Annexure 1 : Important instructions regarding mock trading session

Particulars	Details
Password	Default password shall be "Neat@EG1"
No Financial Obligation:	Trades during mock sessions will not result in any fund pay-in or pay-out.
Live Updates:	Visit www.nseindia.com for any session-related updates.
Support:	For queries, call Toll-Free: 1800 266 0050 (Option 1).

Annexure 2: Interactive Parameters for Login

National Stock Exchange of India Limited

Primary (BKC) / DR site

Gateway Router IP Address	Port
172.19.14.85	11887

Gateway IPs Subnet ranges –

Network	172.19.14.0
Mask	255.255.255.128
Port	11860

Annexure 3: Parameters for market data broadcast for EGR segment

Combined broadcast - Price volume (5 depth 1 second refresh), other related data, master updates, market open/close status message broadcast etc.				
	Source 1		Source 2	
Stream	Multicast IP Address	Broadcast Port	Multicast IP Address	Broadcast Port
EGR	239.50.50.63	10863	239.50.50.68	10868

Annexure 4: Installation procedure for NEATPlus EGR Version 1.0.0

The respective EXE and master files are available for download in the NSE EXTRANET path mentioned below:

Exe/master files	Version / Setup Files	Path on Extranet
NEAT	NEAT EG Version 1.0.0	/egftp/egcommon/NEATPlus100
NEAT Adapter	NA_1.0.25_Setup.exe	/egftp /egcommon/NeatAdapter/
Security & participant master file	security_eg.gz	egftp/egcommon/ntneat
	participant_eg.gz	

National Stock Exchange of India Limited

Pre-requisites:

- Application will support OS – Upto Windows 10
- Redistributable package should be downloaded from <https://www.microsoft.com/en-us/download/details.aspx?id=48145> and installed on Desktop system before installing Neat EGR TWS exe
 - For 32 bit system - vc_redist.x86.exe
 - For 64 bit system - vc_redist.x64.exe
- Recommended resolution for NeatPlusEGR TWS is 1024 X 768

Installation:

- Download the setup file 'NEATEGTWSSetup.exe' to your hard disc in the root directory (i.e. C:\ or D:\ or E:\).
- Go to the drive where NEATEGTWSSetup.exe is copied.
- Double click on the NEATEGTWSSetup.exe.
- The files will be extracted with the window pop up 'NEATPlusEG Installer 1.0.0: Extracting Files'.
- It will be followed by 'NEAT-EGR Version 1.0.0 Installer' pop up window. Installation drive (where application will be installed) will be C: by default.
- The user can change the default installation drive to any other local drives (e.g. D: or E:)
- Click on 'Install' button on this pop-up window and follow the installation instructions.
- Message of successful installation will be displayed once the complete application is installed.
- The user can run NEAT-EG TWS application by double clicking on either of the following:
 - a. NEAT-EG TWS shortcut icon created on the desktop.
 - b. NEAT-EG TWS entry in the 'Programs' sub-menu of the 'Start' menu.
 - c. NEAT-EG.exe located in the NEATEGDB-TWS directory in the installation drive.

Updating the new version with latest data:

- Download following files from NSE EXTRANET path egftp/egcommon/ntneat onto the logon drive:
 - 1) security_eg.gz
 - 2) participant_eg.gz
- Unzip the above files
- From the log on screen click on the "UPLOAD" button to update contracts and participants details.

Annexure – 5

Important guidelines in case of switchover of trading system to Disaster Recovery (DR) Site

1. Kindly note below points after switch over to DR site:
 - a. Trades of primary site will be available in Previous Trades window.
 - b. Trades can be modified/cancelled using Multiple Trade Modification and Cancellation window respectively.

National Stock Exchange of India Limited

- c. Messages of primary site will be available in TWS Message Area.
2. If user renames or deletes the User folder and re-login the NEAT terminal, then data of primary site shall not be available in the functional window as mentioned above point.