

National Stock Exchange of India Limited

Circular

Department: ELECTRONIC GOLD RECEIPTS	
Download Ref No: NSE/EGR/74801	Date: June 19, 2026
Circular Ref. No: 16/2026	

All Members,

Mock trading on Saturday, June 20, 2026 – No new version release

Exchange will be conducting a mock trading session in the Electronic Gold Receipts (EGR) segment on Saturday, June 20, 2026 as per following schedule:

Mock Date: June 20, 2026	
Particulars	Time in Hrs
Trading Session from Primary Site	-
Pre-open session Open	13:45
Pre-open session Close* <i>*Random closure in last one minute</i>	13:53
Normal Market open time	14:00
Block Deal Window Session open time	14:30
Block Deal Window Session close time	14:45
Auction Market Open Time	14:20
Auction Market Close Time	14:55
Normal Market close time	15:00
Trade modification end time	15:10
Re-login Timings	-
Live Re-login start time	18:30
Live Re-login close time	19:00

Members are required to take note of the below important points:

A) NEAT+ version details

Version	Download Path on NSE Extranet:
1.0.0	/egftp/egcommon/NEATPlus100

National Stock Exchange of India Limited

Members are advised to refer to the following Annexures for important instructions regarding the mock trading:

[Annexure 1: Important instructions regarding mock trading session.](#)

[Annexure 2: Interactive Parameters for Login](#)

[Annexure 3: Parameters for market data broadcast for EGR segment](#)

[Annexure 4: Installation procedure for NEATPlus EG Version 1.0.0](#)

For and on behalf of
National Stock Exchange of India Limited

Aarti Surve
Chief Manager

Toll Free No	Email id
1800-266-0050 (Option1)	msm@nse.co.in

Annexure 1 : Important instructions regarding mock trading session

Particulars	Details
Password	Default password shall be "Neat@EG1"
No Financial Obligation:	Trades during mock sessions will not result in any fund pay-in or pay-out.
Live Updates:	Visit www.nseindia.com for any session-related updates.
Support: Extranet / Member portal availability	For queries, call Toll-Free: 1800 266 0050 (Option 1). Connect2NSE and Extranet facility shall not be available from 11:30 am till end of mock session. Extranet API shall not be available from 11:30 am to 01:00 pm.

Annexure 2: Interactive Parameters for Login

Primary (BKC) / DR site

Gateway Router IP Address	Port
172.19.14.86	11887

Gateway IPs Subnet ranges –

National Stock Exchange of India Limited

Network	172.19.14.0
Mask	255.255.255.128
Port	11860

Annexure 3: Parameters for market data broadcast for EGR segment

Combined broadcast - Price volume (5 depth 1 second refresh), other related data, master updates, market open/close status message broadcast etc.				
	Source 1		Source 2	
Stream	Multicast IP Address	Broadcast Port	Multicast IP Address	Broadcast Port
EGR	239.50.50.63	10863	239.50.50.68	10868

Annexure 4: Installation procedure for NEATPlus EGR Version 1.0.0

The respective EXE and master files are available for download in the NSE EXTRANET path mentioned below:

Exe/master files	Version / Setup Files	Path on Extranet
NEAT	NEAT EG Version 1.0.0	/egftp/egcommon/NEATPlus100
NEAT Adapter	NA_1.0.25_Setup.exe	/egftp /egcommon/NeatAdapter/
Security & participant master file	security_eg.gz	egftp/egcommon/ntneat
	participant_eg.gz	

Pre-requisites:

- Application will support OS – Upto Windows 10
- Redistributable package should be downloaded from <https://www.microsoft.com/en-us/download/details.aspx?id=48145> and installed on Desktop system before installing Neat EGR TWS exe
 - For 32 bit system - vc_redist.x86.exe
 - For 64 bit system - vc_redist.x64.exe
- Recommended resolution for NeatPlusEGR TWS is 1024 X 768

National Stock Exchange of India Limited

Installation:

- Download the setup file 'NEATEGTWSSetup.exe' to your hard disc in the root directory (i.e. C:\ or D:\ or E:\).
- Go to the drive where NEATEGTWSSetup.exe is copied.
- Double click on the NEATEGTWSSetup.exe.
- The files will be extracted with the window pop up 'NEATPlusEG Installer 1.0.0: Extracting Files'.
- It will be followed by 'NEAT-EGR Version 1.0.0 Installer' pop up window. Installation drive (where application will be installed) will be C: by default.
- The user can change the default installation drive to any other local drives (e.g. D: or E:)
- Click on 'Install' button on this pop-up window and follow the installation instructions.
- Message of successful installation will be displayed once the complete application is installed.
- The user can run NEAT-EG TWS application by double clicking on either of the following:
 - a. NEAT-EG TWS shortcut icon created on the desktop.
 - b. NEAT-EG TWS entry in the 'Programs' sub-menu of the 'Start' menu.
 - c. NEAT-EG.exe located in the NEATEGDB-TWS directory in the installation drive.

Updating the new version with latest data:

- Download following files from NSE EXTRANET path egftp/egcommon/ntneat onto the logon drive:
 - 1) security_eg.gz
 - 2) participant_eg.gz
- Unzip the above files
- From the log on screen click on the "UPLOAD" button to update contracts and participants details.