

National Stock Exchange of India Limited

Circular

Department: ELECTRONIC GOLD RECEIPTS	
Download Ref No: NSE/EGR/75635	Date: August 07, 2026
Circular Ref. No: 23/2026	

All Members,

Mock trading on Saturday, August 08, 2026 – No new version release

Exchange will be conducting a mock trading session in the Electronic Gold Receipts (EGR) segment on Saturday, August 08, 2026 as per following schedule:

Mock Date: August 08, 2026	
Particulars	Time in Hrs
Trading Session-1 from Primary Site	-
Pre-open session Open	10:45
Pre-open session Close* <i>*Random closure in last one minute</i>	10:53
Normal Market open time	11:00
Block Deal Window Session open time	11:45
Block Deal Window Session-1 close time	12:00
Auction Market Open Time	12:15
Auction Market Close Time	13:00
Normal Market close time	13:30
Trading Session-2 from DR Site	-
Pre-open session Open	14:15
Pre-open session Close* <i>*Random closure in last one minute</i>	14:23
Normal Market open time	14:30
Normal Market close time	15:30
Trade modification end time	15:40
Re-login Timings	-
Live Re-login start time	16:30
Live Re-login close time	17:00

Members are required to take note of the below important points:

National Stock Exchange of India Limited

A) NEAT+ version details

Version	Download Path on NSE Extranet:
1.0.0	/egftp/egcommon/NEATPlus100

Members are advised to refer to the following Annexures for important instructions regarding the mock trading:

[Annexure 1: Important instructions regarding mock trading session.](#)

[Annexure 2: Interactive Parameters for Login](#)

[Annexure 3: Parameters for market data broadcast for EGR segment](#)

[Annexure 4: Installation procedure for NEATPlus EG Version 1.0.0](#)

[Annexure 5: Important guidelines in case of switchover of trading system to Disaster Recovery \(DR\) Site](#)

For and on behalf of
National Stock Exchange of India Limited

Khushal Shah
Associate Vice President

Toll Free No	Email id
1800-266-0050 (Option1)	msm@nse.co.in

Annexure 1 : Important instructions regarding mock trading session

Particulars	Details
Password	Default password shall be "Neat@EG1"
No Financial Obligation:	Trades during mock sessions will not result in any fund pay-in or pay-out.
Live Updates:	Visit www.nseindia.com for any session-related updates.
Extranet / Member portal availability	Connect2NSE and Extranet facility shall not be available from 14:30 hours till end of mock session. Extranet API shall not be available from 14:30 to 15:30 hours.
Support:	For queries, call Toll-Free: 1800 266 0050 (Option 1).

Annexure 2: Interactive Parameters for Login

Primary (BKC) / DR site

Gateway Router IP Address	Port
---------------------------	------

National Stock Exchange of India Limited

172.19.14.86

11887

Gateway IPs Subnet ranges –

Network	172.19.14.0
Mask	255.255.255.128
Port	11860

Annexure 3: Parameters for market data broadcast for EGR segment

Combined broadcast - Price volume (5 depth 1 second refresh), other related data, master updates, market open/close status message broadcast etc.				
	Source 1		Source 2	
Stream	Multicast IP Address	Broadcast Port	Multicast IP Address	Broadcast Port
EGR	239.50.50.63	10863	239.50.50.68	10868

Annexure 4: Installation procedure for NEATPlus EGR Version 1.0.0

The respective EXE and master files are available for download in the NSE EXTRANET path mentioned below:

Exe/master files	Version / Setup Files	Path on Extranet
NEAT	NEAT EG Version 1.0.0	/egftp/egcommon/NEATPlus100
NEAT Adapter	NA_1.0.25_Setup.exe	/egftp /egcommon/NeatAdapter/
Security & participant master file	security_eg.gz	egftp/egcommon/ntneat
	participant_eg.gz	

Pre-requisites:

- Application will support OS – Upto Windows 10

National Stock Exchange of India Limited

- Redistributable package should be downloaded from <https://www.microsoft.com/en-us/download/details.aspx?id=48145> and installed on Desktop system before installing Neat EGR TWS exe
 - For 32 bit system - vc_redist.x86.exe
 - For 64 bit system - vc_redist.x64.exe
- Recommended resolution for NeatPlusEGR TWS is 1024 X 768

Installation:

- Download the setup file 'NEATEGTWSSetup.exe' to your hard disc in the root directory (i.e. C:\ or D:\ or E:\).
- Go to the drive where NEATEGTWSSetup.exe is copied.
- Double click on the NEATEGTWSSetup.exe.
- The files will be extracted with the window pop up 'NEATPlusEG Installer 1.0.0: Extracting Files'.
- It will be followed by 'NEAT-EGR Version 1.0.0 Installer' pop up window. Installation drive (where application will be installed) will be C: by default.
- The user can change the default installation drive to any other local drives (e.g. D: or E:)
- Click on 'Install' button on this pop-up window and follow the installation instructions.
- Message of successful installation will be displayed once the complete application is installed.
- The user can run NEAT-EG TWS application by double clicking on either of the following:
 - a. NEAT-EG TWS shortcut icon created on the desktop.
 - b. NEAT-EG TWS entry in the 'Programs' sub-menu of the 'Start' menu.
 - c. NEAT-EG.exe located in the NEATEGDB-TWS directory in the installation drive.

Updating the new version with latest data:

- Download following files from NSE EXTRANET path egftp/egcommon/ntneat onto the logon drive:
 - 1) security_eg.gz
 - 2) participant_eg.gz
- Unzip the above files
- From the log on screen click on the "UPLOAD" button to update contracts and participants details.

Annexure – 5

Important guidelines in case of switchover of trading system to Disaster Recovery (DR) Site

1. Kindly note below points after switch over to DR site:
 - a. Trades of primary site will be available in Previous Trades window.
 - b. Trades can be modified/cancelled using Multiple Trade Modification and Cancellation window respectively.
 - c. Messages of primary site will be available in TWS Message Area.
2. If user renames or deletes the User folder and re-login the NEAT terminal, then data of primary site shall not be available in the functional window as mentioned above point.