

National Stock Exchange of India Limited

Circular

Department: ELECTRONIC GOLD RECEIPTS	
Download Ref No: NSE/EGR/76419	Date: September 18, 2026
Circular Ref. No: 32/2026	

All Members,

Mock trading on Saturday, September 19, 2026 – No new version release

Exchange will be conducting a mock trading session in the Electronic Gold Receipts (EGR) segment on Saturday, September 19, 2026.

Mock Date: September 19, 2026	
Particulars	Time in Hrs
Trading Session from DR Site	-
Pre-open session Open	11:15
Pre-open session Close* <i>*Random closure in last one minute</i>	11:23
Normal Market open time	11:30
Block Deal Window Session open time	12:00
Block Deal Window Session close time	12:15
Auction Market Open Time	11:45
Auction Market Close Time	12:25
Normal Market close time	12:30
Trade modification end time	12:40
Re-login Timings	-
Live Re-login start time	14:00
Live Re-login close time	14:30

Members are required to take note of the below important points:

A) NEAT+ version details

Version	Download Path on NSE Extranet
1.0.1	/egftp/egcommon/NEATPlus101

National Stock Exchange of India Limited

Members are requested to refer updated NEATPlus installation procedure as per the circular [NSE/MSD/76159](#) dated September 03, 2026.

Members are advised to refer to the following Annexures for important instructions regarding the mock trading:

[Annexure 1: Important instructions regarding mock trading session.](#)

[Annexure 2: Interactive Parameters for Login](#)

[Annexure 3: Parameters for market data broadcast for EGR segment](#)

[Annexure 4: Installation procedure for NEATPlus EG Version 1.0.1](#)

For and on behalf of
National Stock Exchange of India Limited

Khushal Shah
Associate Vice President

Toll Free No	Email id
1800-266-0050 (Option1)	msm@nse.co.in

Annexure 1 : Important instructions regarding mock trading session

Particulars	Details
Password	Default password shall be "Neat@EG1"
Installation Guide	Available on Extranet at /egftp/egcommon/Installation_Procedure
No Financial Obligation:	Trades during mock sessions will not result in any fund pay-in or pay-out.
Live Updates:	Visit www.nseindia.com for any session-related updates.
Support:	For queries, call Toll-Free: 1800 266 0050 (Option 1).
Extranet / Member portal availability	Connect2NSE(member portal) facility shall not be available from 19:00 hours to 23:00 hours. Extranet API shall not be available from 11:30 to 14:00 hours and 19:00 to 23:00 hours.

Annexure 2: Interactive Parameters for Login

Primary (BKC) / DR site

Gateway Router IP Address	Port
---------------------------	------

National Stock Exchange of India Limited

172.19.14.86

11887

Gateway IPs Subnet ranges –

Network	172.19.14.0
Mask	255.255.255.128
Port	11860

Annexure 3: Parameters for market data broadcast for EGR segment

Combined broadcast - Price volume (5 depth 1 second refresh), other related data, master updates, market open/close status message broadcast etc.

	Source 1		Source 2	
Stream	Multicast IP Address	Broadcast Port	Multicast IP Address	Broadcast Port
EGR	239.50.50.63	10863	239.50.50.68	10868

Annexure 4: Installation procedure for NEATPlus EGR Version 1.0.1

The respective EXE and master files are available for download in the NSE EXTRANET path mentioned below:

Exe/master files	Version / Setup Files	Path on Extranet
NEAT	NEAT EG Version 1.0.1	/egftp/egcommon/NEATPlus101
NEAT Adapter	NA_1.0.25_Setup.exe	/egftp /egcommon/NeatAdapter/
Security & participant master file	security_eg.gz	egftp/egcommon/ntneat
	participant_eg.gz	

Pre-requisites:

National Stock Exchange of India Limited

- Application will support OS –Windows 10 and Windows 11
- Redistributable package should be downloaded from <https://visualstudio.microsoft.com/downloads/#microsoft-visual-c-v14-redistributable> and installed on Desktop system before installing Neat EGR TWS exe
 - For 32 bit system - vc_redist.x86.exe
 - For 64 bit system - vc_redist.x64.exe
- Recommended resolution for NeatPlusEGR TWS is 1024 X 768
- Recommended RAM/Memory – 16GB

Installation:

- Download the setup file 'NEATEGTWSSetup.exe' to your hard disc in the root directory (i.e. C:\ or D:\ or E:\).
- Go to the drive where NEATEGTWSSetup.exe is copied.
- Double click on the NEATEGTWSSetup.exe.
- The files will be extracted with the window pop up 'NEATPlusEG Installer 1.0.1: Extracting Files'.
- It will be followed by 'NEAT-EGR Version 1.0.1 Installer' pop up window. Installation drive (where application will be installed) will be C: by default.
- The user can change the default installation drive to any other local drives (e.g. D: or E:)
- Click on 'Install' button on this pop-up window and follow the installation instructions.
- Message of successful installation will be displayed once the complete application is installed.
- The user can run NEAT-EG TWS application by double clicking on either of the following:
 - a. NEAT-EG TWS shortcut icon created on the desktop.
 - b. NEAT-EG TWS entry in the 'Programs' sub-menu of the 'Start' menu.
 - c. NEAT-EG.exe located in the NEATEGDB-TWS directory in the installation drive.