

National Stock Exchange of India Limited

Circular

Department: ELECTRONIC GOLD RECEIPTS	
Download Ref No: NSE/EGR/76818	Date: October 09, 2026
Circular Ref. No: 37/2026	

All Members,

Mock trading on Saturday, October 10, 2026 – New version of NEAT+ 1.0.2

In continuation to circular (Download No. 74203) dated May 13, 2026, Exchange will be conducting a mock trading session in the Electronic Gold Receipts (EGR) segment on Saturday, October 10, 2026.

Mock Date: October 10, 2026	
Particulars	Time in Hrs
Trading Session-1 from Primary Site	-
Pre-open session Open	10:45
Pre-open session Close* <i>*Random closure in last one minutes</i>	10:53
Normal Market open time	11:00
Contingency Start	11:45
Contingency Close	13:15
Block Deal Window Session open time	11:25
Block Deal Window Session close time	11:40
Auction Market Open Time	11:10
Auction Market Close Time	11:45
Normal Market close time	14:00
Trading Session-2 from DR Site	-
Pre-open session Open	14:45
Pre-open session Close* <i>*Random closure in last one minutes</i>	14:53
Normal Market open time	15:00
Normal Market close time	15:30
Trade modification end time	15:40
Re-login Timings	-
Live Re-login start time	18:30
Live Re-login close time	19:00

National Stock Exchange of India Limited

Members are required to take note of the below important points:

A) Members are requested to refer circular NSE/EGR/76507 dated September 24, 2026, regarding ‘dissemination of Quantity Freeze Report for Electronic Gold Receipt Segment’. The same shall be applicable in the mock of October 10, 2026 and in LIVE from October 12, 2026 onwards. The file shall be available in Extranet path by 07:00 hours on October 10, 2026.

B) New NEAT+ version release details:

Version	Availability	Download Path on NSE Extranet
1.0.2	From October 09, 2026, 18:00 hrs	/egftp/egcommon/NEATPlus102

C) Version migration timeline :

Version	Release date	Discontinuation date
1.0.1	From September 05, 2026	November 14, 2026 (mock)
1.0.2 (recommended)	From October 9, 2026	-

Members are advised to refer to the following Annexures for important instructions regarding the mock trading:

[Annexure 1: Important instructions regarding mock trading session.](#)

[Annexure 2: Interactive Parameters for Login](#)

[Annexure 3: Parameters for market data broadcast for EGR segment](#)

[Annexure 4: Installation procedure for NEATPlus EG Version 1.0.2](#)

[Annexure 5: Important guidelines in case of switchover of trading system to Disaster Recovery \(DR\) Site](#)

For and on behalf of

National Stock Exchange of India Limited

Khushal Shah

Associate Vice President

Toll Free No	Email id
1800-266-0050 (Option1)	msm@nse.co.in

Annexure 1 : Important instructions regarding mock trading session

Particulars	Details
Password	Default password shall be “Neat@EG1”

National Stock Exchange of India Limited

Installation Guide	Available on Extranet at /egftp/egcommon/Installation_Procedure
No Financial Obligation:	Trades during mock sessions will not result in any fund pay-in or pay-out.
Live Updates:	Visit www.nseindia.com for any session-related updates.
Support:	For queries, call Toll-Free: 1800 266 0050 (Option 1).
Extranet / Member portal availability	Connect2NSE and Extranet facility shall not be available from 12:30 hours to 21:00 hours. Extranet API shall not be available from 12:30 to 14:00 hours.

Annexure 2: Interactive Parameters for Login

Primary (BKC) / DR site

Gateway Router IP Address	Port
172.19.14.86	11887

Gateway IPs Subnet ranges –

Network	172.19.14.0
Mask	255.255.255.128
Port	11860

Annexure 3: Parameters for market data broadcast for EGR segment

Combined broadcast - Price volume (5 depth 1 second refresh), other related data, master updates, market open/close status message broadcast etc.				
	Source 1		Source 2	
Stream	Multicast IP Address	Broadcast Port	Multicast IP Address	Broadcast Port
EGR	239.50.50.63	10863	239.50.50.68	10868

National Stock Exchange of India Limited

Annexure 4: Installation procedure for NEATPlus EGR Version 1.0.2

The respective EXE and master files are available for download in the NSE EXTRANET path mentioned below:

Exe/master files	Version / Setup Files	Path on Extranet
NEAT	NEAT EG Version 1.0.2	/egftp/egcommon/NEATPlus102
NEAT Adapter	NA_1.0.25_Setup.exe	/egftp /egcommon/NeatAdapter/
Security & participant master file	security_eg.gz	egftp/egcommon/ntneat
	participant_eg.gz	

Pre-requisites:

- Application will support OS –Windows 10 and Windows 11
- Redistributable package should be downloaded from <https://visualstudio.microsoft.com/downloads/#microsoft-visual-c-v14-redistributable> and installed on Desktop system before installing Neat EGR TWS exe
 - For 32 bit system - vc_redist.x86.exe
 - For 64 bit system - vc_redist.x64.exe
- Recommended resolution for NeatPlusEGR TWS is 1024 X 768
- Recommended RAM/Memory – 16GB

Installation:

- Download the setup file 'NEATEGTWSSetup.exe' to your hard disc in the root directory (i.e. C:\ or D:\ or E:\).
- Go to the drive where NEATEGTWSSetup.exe is copied.
- Double click on the NEATEGTWSSetup.exe.
- The files will be extracted with the window pop up 'NEATPlusEG Installer 1.0.1: Extracting Files'.
- It will be followed by 'NEAT-EGR Version 1.0.1 Installer' pop up window. Installation drive (where application will be installed) will be C: by default.
- The user can change the default installation drive to any other local drives (e.g. D: or E:)
- Click on 'Install' button on this pop-up window and follow the installation instructions.
- Message of successful installation will be displayed once the complete application is installed.
- The user can run NEAT-EG TWS application by double clicking on either of the following:
 - a. NEAT-EG TWS shortcut icon created on the desktop.
 - b. NEAT-EG TWS entry in the 'Programs' sub-menu of the 'Start' menu.
 - c. NEAT-EG.exe located in the NEATEGDB-TWS directory in the installation drive.

National Stock Exchange of India Limited

Annexure – 5

Important guidelines in case of switchover of trading system to Disaster Recovery (DR) Site

1. Kindly note below points after switch over to DR site:
 - a. Trades of primary site will be available in Previous Trades window.
 - b. Trades can be modified/cancelled using Multiple Trade Modification and Cancellation window respectively.
 - c. Messages of primary site will be available in TWS Message Area.
2. If user renames or deletes the User folder and re-login the NEAT terminal, then data of primary site shall not be available in the functional window as mentioned above point.