National Stock Exchange of India Limited

Circular

Department: ELECTRONIC GOLD RECEIPTS	
Download Ref No: NSE/EGR/77200	Date: October 30, 2026
Circular Ref. No: 40/2026	

All Members,

Mock trading from BCP/DR site on Saturday, October 31, 2026

Exchange shall be conducting a mock trading session on Saturday, October 31, 2026 from Primary and BCP site. The mock will be followed by a re-login session from Primary site in order to avoid login problems on Monday, November 02, 2026. The schedule of the mock trading is as follows:

Mock Date: October 31, 2026	
Particulars	**Time in Hrs**
Trading Session-1 from Primary Site	**-**
Pre-open session Open	**08:45**
Pre-open session Close* * *Random closure in last one minute*	**08:53**
Normal Market open time	**09:00**
Normal Market close time	**12:00**
Trading Session-2 from DR Site	**-**
Pre-open session Open	**12:45**
Pre-open session Close* * *Random closure in last one minute*	**12:53**
Normal Market open time	**13:00**
Auction Market Open Time	**14:30**
Auction Market Close Time	**15:15**
Normal Market close time	**17:00**
Trade modification end time	17:15
Re-login Timings	-
Live Re-login start time	18:30
Live Re-login close time	19:00

Members are required to perform the following:

Non-Confidential

National Stock Exchange of India Limited

- **For connecting to Primary/DR site, no changes in NEAT Adapter settings are required. Settings of live session as of Friday, October 30, 2026 in NEAT Adapter shall be retained to connect to all the above sessions of Primary/DR site.**

- Members are requested to note that Exchange shall shift its operation from primary site to DR site during the mock session and it shall be a non-graceful shutdown from the primary site. In case of such event necessary action should be taken at member's end as stated in circular NSE/MSD/48662 dated June 18, 2021 to bring their systems into a consistent state.

- All the outstanding orders shall be purged before the start of trading from BCP site. Members using NNF software should clear the outstanding orders of session 1 in their systems before trading from BCP site.

Members are advised to refer to the following Annexures for important instructions regarding the mock trading:

Annexure 1: Important instructions regarding mock trading session.
Annexure 2: Interactive Parameters for Login
Annexure 3: Parameters for market data broadcast for EGR segment
Annexure 4: Installation procedure for NEATPlus EG Version 1.0.2
Annexure 5: Important guidelines in case of switchover of trading system to Disaster Recovery (DR) Site

For and on behalf of
National Stock Exchange of India Limited

Khushal Shah
Associate Vice Presiden

Toll Free No	Email id
1800-266-0050 (Option1)	msm@nse.co.in

Annexure 1 : Important instructions regarding mock trading session

Particulars	Details
Password	Default password shall be “Neat@EG1”
No Financial Obligation:	Trades during mock sessions will not result in any fund pay-in or pay-out.
Live Updates:	Visit www.nseindia.com for any session-related updates.
Support: Extranet / Member portal availability	For queries, call Toll-Free: 1800 266 0050 (Option 1). Connect2NSE and Extranet facility shall not be available from 11:15 am to 12:30 pm and 06:00 pm to 08:00 pm.

Annexure 2: Interactive Parameters for Login

Non-Confidential

Primary (BKC) / DR site

Gateway Router IP Address	Port
172.19.14.86	**11887**

Gateway IPs Subnet ranges –

Network	172.19.14.0
Mask	255.255.255.128
Port	11860

Annexure 3: Parameters for market data broadcast for EGR segment

Combined broadcast - Price volume (5 depth 1 second refresh), other related data, master updates, market open/close status message broadcast etc.				
	Source 1		**Source 2**	
Stream	**Multicast IP Address**	**Broadcast Port**	**Multicast IP Address**	**Broadcast Port**
EGR	239.50.50.63	10863	239.50.50.68	10868

Annexure 4: Installation procedure for NEATPlus EGR Version 1.0.0

The respective EXE and master files are available for download in the NSE EXTRANET path mentioned below:

Exe/master files	**Version / Setup Files**	**Path on Extranet**
NEAT	NEAT EG Version 1.0.2	/egftp/egcommon/NEATPlus102
NEAT Adapter	NA_1.0.25_Setup.exe	/egftp /egcommon/NeatAdapter/
Security & participant master file	security_eg.gz	egftp/egcommon/ntneat
	participant_eg.gz	

Pre-requisites:

- Application will support OS – Upto Windows 10

Non-Confidential

- Redistributable package should be downloaded from https://www.microsoft.com/en-us/download/details.aspx?id=48145 and installed on Desktop system before installing Neat EGR TWS exe
  - For 32 bit system - vc_redist.x86.exe
  - For 64 bit system - vc_redist.x64.exe
- Recommended resolution for NeatPlusEGR TWS is 1024 X 768

Installation:

- Download the setup file 'NEATEGTWSSetup.exe' to your hard disc in the root directory (i.e. C:\ or D:\ or E:\).
- Go to the drive where NEATEGTWSSetup.exe is copied.
- Double click on the NEATEGTWSSetup.exe.
- The files will be extracted with the window pop up 'NEATPlusEG Installer 1.0.0: Extracting Files'.
- It will be followed by 'NEAT-EGR Version 1.0.0 Installer' pop up window. Installation drive (where application will be installed) will be C: by default.
- The user can change the default installation drive to any other local drives (e.g. D: or E:)
- Click on 'Install' button on this pop-up window and follow the installation instructions.
- Message of successful installation will be displayed once the complete application is installed.
- The user can run NEAT-EG TWS application by double clicking on either of the following:
  a. NEAT-EG TWS shortcut icon created on the desktop.
  b. NEAT-EG TWS entry in the 'Programs' sub-menu of the 'Start' menu.
  c. NEAT-EG.exe located in the NEATEGDB-TWS directory in the installation drive.

Updating the new version with latest data:

- Download following files from NSE EXTRANET path egftp/egcommon/ntneat onto the logon drive:
  1) security_eg.gz
  2) participant_eg.gz
- Unzip the above files
- From the log on screen click on the "UPLOAD" button to update contracts and participants details.

Annexure – 5

Important guidelines in case of switchover of trading system to Disaster Recovery (DR) Site

1. Kindly note below points after switch over to DR site:
   a. Trades of primary site will be available in Previous Trades window.
   b. Trades can be modified/cancelled using Multiple Trade Modification and Cancellation window respectively.
   c. Messages of primary site will be available in TWS Message Area.
2. If user renames or deletes the User folder and re-login the NEAT terminal, then data of primary site shall not be available in the functional window as mentioned above point.

Non-Confidential