National Stock Exchange of India Limited

Circular

Department: ELECTRONIC GOLD RECEIPTS	
Download Ref No: NSE/EGR/77417	**Date: November 13, 2026**
Circular Ref. No: 42/2026	

All Members,

Mock trading on Saturday, November 14, 2026 – No new version release

Exchange will be conducting a mock trading session in the Electronic Gold Receipts (EGR) segment on Saturday, November 14, 2026.

Mock Date: November 14, 2026	
Particulars	**Time in Hrs**
Trading Session from DR Site	**-**
Pre-open session Open	**12:15**
Pre-open session Close* **Random closure in last one minutes*	**12:23**
Normal Market open time	**12:30**
Block Deal Window Session open time	13:05
Block Deal Window Session close time	13:20
Auction Market Open Time	13:30
Auction Market Close Time	14:15
Normal Market close time	**14:30**
Trade modification end time	14:40
Re-login Timings	-
Live Re-login start time	16:00
Live Re-login close time	16:30

Members are required to take note of the below important points:

A) NEAT+ version details :

Version	Download Path on NSE Extranet	Discontinuation date
1.0.1	/egftp/egcommon/NEATPlus101	November 14, 2026 (mock)
1.0.2 (recommended)	/egftp/egcommon/NEATPlus102	-

National Stock Exchange of India Limited

Members are advised to refer to the following Annexures for important instructions regarding the mock trading:

Annexure 1: Important instructions regarding mock trading session.
Annexure 2: Interactive Parameters for Login
Annexure 3: Parameters for market data broadcast for EGR segment
Annexure 4: Installation procedure for NEATPlus EG Version 1.0.2

For and on behalf of
National Stock Exchange of India Limited

Khushal Shah
Associate Vice President

Toll Free No	Email id
1800-266-0050 (Option1)	msm@nse.co.in

Annexure 1 : Important instructions regarding mock trading session

Particulars	Details
Password	Default password shall be “Neat@EG1”
Installation Guide	Available on Extranet at /egftp/egcommon/Installation_Procedure
No Financial Obligation:	Trades during mock sessions will not result in any fund pay-in or pay-out.
Live Updates:	Visit www.nseindia.com for any session-related updates.
Extranet / Member portal availability	Connect2NSE and Extranet facility shall not be available from 19:00 hours to 22:00 hours. Extranet API shall not be available from 19:00 to 22:00 hours.
Support:	For queries, call Toll-Free: 1800 266 0050 (Option 1).

Annexure 2: Interactive Parameters for Login

Primary (BKC) / DR site

Gateway Router IP Address	Port
172.19.14.86	**11887**

Gateway IPs Subnet ranges –

Non-Confidential

National Stock Exchange of India Limited

Network	172.19.14.0
Mask	255.255.255.128
Port	11860

Annexure 3: Parameters for market data broadcast for EGR segment

Combined broadcast - Price volume (5 depth 1 second refresh), other related data, master updates, market open/close status message broadcast etc.				
	Source 1		**Source 2**	
Stream	**Multicast IP Address**	**Broadcast Port**	**Multicast IP Address**	**Broadcast Port**
EGR	239.50.50.63	10863	239.50.50.68	10868

Annexure 4: Installation procedure for NEATPlus EGR Version 1.0.2

The respective EXE and master files are available for download in the NSE EXTRANET path mentioned below:

Exe/master files	**Version / Setup Files**	**Path on Extranet**
NEAT	NEAT EG Version 1.0.2	/egftp/egcommon/NEATPlus102
NEAT Adapter	NA_1.0.25_Setup.exe	/egftp /egcommon/NeatAdapter/
Security & participant master file	security_eg.gz	egftp/egcommon/ntneat
	participant_eg.gz	

Pre-requisites:

- Application will support OS –Windows 10 and Windows 11
- Redistributable package should be downloaded from https://visualstudio.microsoft.com/downloads/#microsoft-visual-c-v14-redistributable and installed on Desktop system before installing Neat EGR TWS exe
  - For 32 bit system - vc_redist.x86.exe
  - For 64 bit system - vc_redist.x64.exe
- Recommended resolution for NeatPlusEGR TWS is 1024 X 768

Non-Confidential

- Recommended RAM/Memory – 16GB

Installation:

- Download the setup file 'NEATEGTWSSetup.exe' to your hard disc in the root directory (i.e. C:\ or D:\ or E:\).
- Go to the drive where NEATEGTWSSetup.exe is copied.
- Double click on the NEATEGTWSSetup.exe.
- The files will be extracted with the window pop up 'NEATPlusEG Installer 1.0.1: Extracting Files'.
- It will be followed by 'NEAT-EGR Version 1.0.1 Installer' pop up window. Installation drive (where application will be installed) will be C: by default.
- The user can change the default installation drive to any other local drives (e.g. D: or E:)
- Click on 'Install' button on this pop-up window and follow the installation instructions.
- Message of successful installation will be displayed once the complete application is installed.
- The user can run NEAT-EG TWS application by double clicking on either of the following:
    a. NEAT-EG TWS shortcut icon created on the desktop.
    b. NEAT-EG TWS entry in the 'Programs' sub-menu of the 'Start' menu.
    c. NEAT-EG.exe located in the NEATEGDB-TWS directory in the installation drive.

Non-Confidential