

National Stock Exchange of India Limited

Circular

Department: SECURITIES LENDING AND BORROWING MARKET	
Download Ref No: NSE/SLBS/74575	Date: June 05, 2026
Circular Ref. No: 15/2026	

All Members,

Mock trading on Saturday, June 06, 2026 – No new version release

Exchange will be conducting a mock trading session in the SLBM on Saturday, June 06, 2026 as per the following schedule:

Mock Date: June 06, 2026	
Particulars	Time in Hrs
Trading Session-1 from Primary Site	-
Normal Market open time	10:15
Contingency Start Time	11:00
Contingency Close Time	12:30
Normal Market close time	13:00
Trading Session-2 from DR Site	-
Normal Market open time	14:00
Normal Market close time	14:30
Relogin Timings	-
Live Re-login start time	16:00
Live Re-login close time	16:30

Members are requested to refer to circular no. NSE/MSD/74511 dated June 02, 2026 regarding new CA certificate and NSE/MSD/74559 dated June 05, 2026 for new version of Neat Adapter EXE application. Accordingly, members are requested to use the combination of new NEAT adapter version and new ports applicable for SLBM segment as below:

Login through	Dates	Applicable GR PORT
New NEAT Adapter application Version 1.0.28 for Windows Neat Adapter Version 1.0.28 for Linux Neat Adapter	Mandatory from July 06, 2026 (mock)	10889

Members using Direct connection through NNF users, are requested to download and use the new CA certificate which shall be made available by June 5, 2026 (EOD) in Extranet path (/slbftp/slbcommon/Encryption_CA_Certificate/2026_Certificate). Accordingly, members shall ensure readiness of their migration plan by July 06, 2026. **The applicable new interactive parameters to be used with 'New CA certificate':**

National Stock Exchange of India Limited

Segment	Gateway Router		Gateway IPs Subnet ranges		
	IP Address	New Port	Network	Mask	Port
Securities Lending & Borrowing (SLBM)	172.19.14.85	10889	172.19.14.0	255.255.255.128	10860

*Port – This port will support new encryption messages with MD5 checksum removal.

**Port - This port will support new encryption messages with MD5 checksum removal and new immediate Ack request for order related messages.

For other important instructions regarding the mock trading, kindly refer to the following Annexure:

Annexure 1: Important instructions regarding mock trading session.

Annexure 2: Pre-requisites / General guidelines for participating in the Mock environment.

Annexure 3: Important guidelines in case of switchover of trading system to Disaster Recovery (DR) Site.

**For and on behalf of
National Stock Exchange of India Limited**

**Aarti Surve
Chief Manager**

Toll Free No	Email id
1800-266-00-50 (Option 1)	msm@nse.co.in

Annexure – 1

Important Instructions regarding mock trading

Particulars	Details
Connectivity Parameters:	Refer to circular NSE/MSD/73993 dated April 30, 2026 for interactive connectivity details.
Installation Guide:	Available on NSE Extranet at /slbftp/slbcommon/Installation_Procedure.
NEAT Version:	NEAT 1.3.3
Order Purge:	All outstanding orders will be cleared before each session. Members using NNF software must manually clear orders in their systems.
Software Testing:	Refer to circular NSE/MSD/46441 and SEBI circular SEBI/HO/MRD1/DSAP/CIR/P/2020/234. Members may use either Mock Trading or Simulated Environment to meet regulatory requirements.

National Stock Exchange of India Limited

No Financial Obligation:	Trades during mock sessions will not result in any fund pay-in or pay-out.
UCC/PAN Validity:	With reference to Exchange circular NSE/ISC/51754 dated March 24, 2022 and NSE/ISC/52722 dated June 23, 2022 issued by Investor Services Cell and updated from time to time : <ul style="list-style-type: none"> • Only valid and compliant UCC/PAN uploaded and approved before cutoff will be allowed. • For queries, contact uci@nse.co.in. UCC Validation will be skipped during contingency time for order entry.
NOTIS Availability:	The NOTIS application will be accessible during the mock session.
Extranet / Member portal availability	Connect2NSE and Extranet facility shall not be available from 11:30 am till end of mock session. Extranet API shall not be available from 11:30 am to 01:00 pm.
Participation:	Members should participate using all trading software and re-login into live environment to ensure smooth connectivity for Monday, June 08, 2026.
Live Updates:	Visit www.nseindia.com for any session-related updates.
Support:	For queries, call Toll-Free: 1800 266 0050 (Option 1).

Annexure 2

Pre-requisites / General guidelines for participating in the Mock environment

Pre-requisites / General guidelines Heads	Details
Eligibility	All members enabled for trading in the SLBM segment in the live market are automatically eligible for mock trading. Participation is enabled using existing User IDs, IPs, and Box ID mappings from the live environment.
Telnet Connectivity	Ensure you can successfully telnet the Exchange host from the IP address you intend to use.
Box ID Setup	Confirm that the Box ID is created on the IP with appropriate messages for the segment you wish to trade in.
NNF Application Users	If using Non-NEAT Frontend (NNF): a) User ID must be of dealer type. b) It must be converted for NNF. c) It must be mapped with the IP.
Branch/User Limits	Set appropriate branch and user limits from the Corporate Manager Terminal before placing orders in the mock session.

National Stock Exchange of India Limited

Exchange Requests for Mock Participation	<p>Send email requests for the following actions with User ID and segment details:</p> <ul style="list-style-type: none"> a) Pro Enablement b) CTCL Conversion (only dealer IDs) c) Password Reset for Corporate Manager User ID d) Unlocking of Corporate Manager User ID e) Change of Trading Rights (e.g., PRO to CLI, PRO+CLI)
Password Management	<p>Corporate Manager User ID: Exchange will assist with reset/unlock via email.</p> <p>Other User IDs: Members must reset/unlock these themselves using the Corporate Manager Terminal.</p>

Annexure – 3

Important guidelines in case of switchover of trading system to Disaster Recovery (DR) Site

1. Kindly note below points after switch over to DR site:
 - a. Trades of primary site will be available in Previous Trades window.
 - b. Trades can be modified/cancelled using Multiple Trade Modification and Cancellation window respectively.
 - c. Messages of primary site will be available in TWS Message Area.
2. If user renames or deletes the User folder and re-login the NEAT terminal, then data of primary site shall not be available in the functional window as mentioned above point.