

## Annexure 2: Live Details

### Issue details for live session

Company Name	Igarashi Motors India Limited
Symbol	IGARASHI
Series	IS (Non retail category) RS (Retail category – Bid value < or = Rs 2 lacs)
ISIN	INE188B01013
Issue Size	33,20,351 equity shares
Date of Offer	July 12, 2016 & July 13, 2016
Floor Price	Rs. 650
Market Lot	1 Equity share
Tick Size	Rs 0.05

### Non Retail category Bidding details (IS Series)

Bidding session Date	July 12, 2016
Bidding session Time	09:15 Hrs to 15:30 Hrs.
Series	IS (Non retail category)
Date to indicate CARRY FORWARD of unallocated Bids in Non-retail category*	July 13, 2016
Carry Forward Timings	09:15 Hrs to 15:30 Hrs.

\* Trading members who want to carry forward their unallocated non-retail bids on T+1 shall have to modify such bids and opt to carry forward the bids on the NEAT terminal of IPO.

**For further details refer circular NSE/CMTR/31777 dated February 19, 2016.**

### Retail category Bidding details (RS Series)

Bidding session Date	July 13, 2016
Bidding session Time	09:15 Hrs to 15:30 Hrs.
Series	RS (Retail category)
Bidding at Cut-off - 'RS' series	Cut-off available - Default option on order entry screen
Discount to Retail investor bids	Not Applicable
Reservation portion %	10% of offer size

## **TAP Parameters for Live**

Members have the option to use either of the below TAP versions for connecting to Exchange (Live) environment.


### **Windows TAP Software:**

Sr. no.	Setup Name	Version	OS	Extranet path
1	TAP_1.1.4_Setup.exe	<b>1.1.4</b>	<b>Windows</b>	/Common/IPO-OFS/WinTAP
2	TAP_1.1.3_Setup.exe	<b>1.1.3</b>	<b>Windows</b>	/Common/IPO/IntegratedTAP/Windows)

### **Linux TAP Software:**

Sr. no.	Setup Name	Version	OS	Extranet path
2	TAP_7.0.7_Setup.sh, TAP_7.0.7_SetupFiles.zip	<b>7.0.7</b>	<b>Linux</b>	/Common/IPO-OFS/LinTAP
2	TAP_7.0.5_Setup.sh, TAP_7.0.5_SetupFiles.zip	<b>7.0.5</b>	<b>Linux</b>	/Common/IPO/IntegratedTAP/Linux

## Configuring TAP Software windows version 1.1.4 & Linux – Version 7.0.7:

New TAP Version	TAP configuration
For Windows – Version 1.1.4	For Windows TAP –
Member Code	
Member LAN IP	
WAN IP Provided by NSE	
Please select 'Primary'	
Please select 'Live' for connecting to Live environment	
For Linux – Version 7.0.7	For Linux TAP-
Please select 'Switch to Live Environment'	<pre> ***** [ TAP IPO Configuration Menu ] *****  Broker ID.....[16]  1. Local IP.....[] 2. WAN IP.....[] 3. Box ID.....[0] 4. TAP Port.....[9604] -. FIX Port.....[0] (Not Configurable). -. PRIMARY Configuration.      [Current Configuration]. 6. Switch to BCP Configuration. 7. Switch to Development Configuration. 8. Connection Type.[Lease Line] -. Enable TAP Logging (Not Configurable). 10. Change Broker ID. -. Switch to Live Environment.  [Current Configuration]. 12. Switch to Mock Environment. -. Save. -. Save &amp; exit. 0. Exit. ***** </pre>
<ul style="list-style-type: none"> <li>IPO_TAP_CONFIG_1.0_Setup.exe NOT to be run in case of New Windows TAP Version 1.1.4 &amp; New Linux TAP Version 7.0.7</li> </ul>	

**Configuring Existing TAP Software windows version 1.1.3 & Linux – Version 7.0.5:**  
**(There is no change in this)**

Existing TAP Version	TAP configuration
(For Windows – Version 1.1.3)	For Windows TAP: <ul style="list-style-type: none"> <li>Use 'IPO_TAP_CONFIG_1.0_Setup.exe' to connect to Live session, available in following path: (/common/IPO/IntegratedTAP/Windows)</li> <li>To configure please refer help document available on the above path (File name : Windows_IPO_TAP_Configurator.docx)</li> </ul>
(For Linux – Version 7.0.5)	For Linux TAP: <ul style="list-style-type: none"> <li>Use 'IPO_TAP_CONFIG_1.0_Setup.sh and IPO_TAP_CONFIG_1.0_Setup.zip' to connect to Live session, available in following path: (/common/IPO/IntegratedTAP/Linux)</li> </ul> <p>To configure please refer help document available on the above path (File name : Linux_IPO_TAP_Configurator.docx)</p>

**Configuring NSE UDP server: (For Broadcast Data Connection)**

Receiving Multicast Address	239.50.50.41
Receiving UDP Port	10841

The screenshot shows the 'NSE UDP Broadcast Server Configuration v3.04.00' dialog box. It contains several input fields and buttons. Annotations with arrows point to specific fields:

- Sending Multicast Address:** An annotation box says 'To be configured at Member's N/W'.
- Local IP Address towards Host:** An annotation box says 'WAN IP Provided by NSE'.
- Local IP Address towards NEAT:** An annotation box says 'Member LAN IP'.
- Host:** A dropdown menu showing '0'.
- Receiving UDP Port No.:** An annotation box says 'Input as 10841'.
- Receiving Multicast Address:** An annotation box says 'Input as 239.50.50.41'.
- Sending UDP Port No.:** An annotation box says 'To be configured at Member's N/W'.

At the bottom of the dialog, there are three buttons: 'Add/Modify', 'OK', and 'Cancel'. Below these buttons is a text box with the placeholder text 'Enter Corresponding Receiving Multicast Address.'.

### **Important Instruction**

- Members are requested to upload the latest *participant.txt* file of Capital Market segment, which will be available on NSE extranet or internet <ftp://ftp.connect2nse.com> (Path: /Common/ntneat) for live purpose.
- Members may please note that all the eligible trading members of the Capital Market segment will be eligible to participate in the live session using their existing Capital Market user id with default password as “NEATPM”.
- In case of queries, members are advised to contact Toll Free no: 1800 266 0053.