

Installation procedure for NEATEGR Version

The respective EXE and master files are available for download in the NSE EXTRANET path mentioned below:

Exe/master files	Path on Extranet
NEAT	/egftp/egcommon/NEATPlusnnn
NEAT Adapter	/egftp /egcommon/NeatAdapter/
Security & participant master file	egftp/egcommon/ntneat

Pre-requisites:

- Application will support OS –Windows 10 and Windows 11
- Redistributable package should be downloaded from <https://visualstudio.microsoft.com/downloads/#microsoft-visual-c-v14-redistributable> and installed on Desktop system before installing Neat EGR TWS exe
 - For 32 bit system - VC_redist.x86.exe
 - For 64 bit system - VC_redist.x64.exe
- Recommended resolution for NeatPlusEGR TWS is 1024 X 768
- Recommended RAM/Memory – 16GB

Installation:

- Download the setup file 'NEATEGTWSSetup.exe' to your hard disc in the root directory (i.e. C:\ or D:\ or E:\).
- Go to the drive where NEATEGTWSSetup.exe is copied.
- Double click on the NEATEGTWSSetup.exe.
- The files will be extracted with the window pop up 'NEATPlusEG Installer n.n.n: Extracting Files'.
- It will be followed by 'NEAT-EGR Version n.n.n Installer' pop up window. Installation drive (where application will be installed) will be C: by default.
- The user can change the default installation drive to any other local drives (e.g. D: or E:)
- Click on 'Install' button on this pop-up window and follow the installation instructions.
- Message of successful installation will be displayed once the complete application is installed.
- The user can run NEAT-EG TWS application by double clicking on either of the following:
 - a. NEAT-EG TWS shortcut icon created on the desktop.
 - b. NEAT-EG TWS entry in the 'Programs' sub-menu of the 'Start' menu.
 - c. NeatEG-TWS.exe located in the NEATEGDB-TWS directory in the installation drive.

Updating the new version with latest data:

- Download following files from NSE EXTRANET path egftp/egcommon/ntneat onto the logon drive:
 - 1) security_eg.gz
 - 2) participant_eg.gz
 - Unzip the above files
- From the log on screen click on the "UPLOAD" button to update contracts and participants details.